
# **DIN Rail DALI Master Controller**

CE PROHS

### Important: Read All Instructions Prior to Installation

#### **Function introduction**



# While built-in DALI PS enabled

Input Voltage	Frequency	Number of DALI Channel	Output Voltage	Output Current	Size(LxWxH)	Ambient Temperature
100-240VAC	50/60Hz	1	16VDC	230mA max	110x53x65mm	-20°C ~ +50°C

# While built-in DALI PS disabled

Input Voltage	Number of DALI Channel	DALI Current Consumption	Size(LxWxH)	Ambient Temperature
5VDC	1	4mA max	110x53x65mm	-20°C ~ +50°C


# Safety & Warnings


- DO NOT install with power applied to device.
- DO NOT expose the device to moisture.
- Supports DT6, DT8 Tc, DT8 XY, DT8 RGBWA control gear device types, DALI-2 input devices
- Each DALI channel supports max 64 control gears, max 64 DALI-2 input devices
- Each DALI channel supports max 16 groups for control gears, 32 groups for input devices, 16 DALI scenes
- Built-in 230mA DALI PS, no extra wiring required
- Easy connect to a Windows PC through USB port

- Built-in battery, built-in RTC, supports timer task configuration
- Supports cycle schedule configuration
- Supports bionic schedule configuration (Human Centric Lighting)
- Waterproof grade: IP20

# Wiring Diagram

# 1) While Use built-in DALI Power Supply





**Note**: please use an USB-A male to USB-B male data cable to connect the controller and the computer as follows:




USB-B male connector

**Note**: When use built-in DALI power supply, please dial both DALI power setting dip switches to "ON" position. The controller can supports up to total 64 control gears and 64 DALI-2 input devices.



70030140



Operation

1) Do wiring according to the wiring diagram and power on the DALI system.

2) Install the "DALI Master" software on the operating computer:

Figure 5 Starting Installation

Cancel


**Figure 6 Complete Installation** 

Brith

KE

Step 1: Run the installation file and select installation mode as shown in Figure 1.

#### Notes:



1) Please install the software according the installation steps, otherwise it can not be started correctly.

**2)** This software is installed to disk C by default, if the installation path is not modified, please run the software as administrator, detailed method is as follows:

Step 1: Right click the desktop icon to to check the properties, switch to "Compatibility" tab, and check item "Run this program as an administrator" as shown in **Figure 7**.

Step 2: Click "OK" to complete the setting as shown in Figure 7.

**3)** If you need to re-install the software, if you need to change the installation path please first uninstall previous installation, otherwise just install to cover the previous installation.

Step 3: Right click "This PC", then click "Management", then click "Device Manager", then you can check whether the installation is successful or not as shown in Figure 11.

🜆 Computer Management (Local	V 🛃 DESKTOP-Q8FQESA
🗸 🎁 System Tools	> 4 Audio inputs and outputs
> 🕑 Task Scheduler	> 🛞 Bluetooth
> 🛃 Event Viewer	> 💻 Computer
> 👸 Shared Folders	> 👝 Disk drives
> 👰 Local Users and Groups	> 🏣 Display adapters
> 🔕 Performance	> DVD/CD-ROM drives
📲 Device Manager	> 🎽 Firmware
🗸 🔄 Storage	> 🛺 Human Interface Devices
📅 Disk Management	> 📹 IDE ATA/ATAPI controllers
> 🛃 Services and Applications	> 📷 Imaging devices
	> 🔤 Keyboards
	> II Mice and other pointing devices
	> 🛄 Monitors
	> 🖵 Network adapters
	> 🚺 Other devices
	Ports (COM & LPT)
	USB-SERIAL CH340 (COM7)

Figure 10 Driver Installation Successful

5) Follow the instruction of the PC configuration software to configure the master controller and control gears, for detailed operation please refer to the user manual of the PC software.

Figure 7 Run this program as an administrator

### 3) INSTALL CH340 DRIVER

Step 1: Connect the USB communication port wire, double click the file "CH341SER.EXE" to install, as shown in Figure 8.

s > STM32 Download Tool (FlyMcu) > CH340 CH341 Driver			
名称 ^	修改日期	美型	大小
🛃 CH341SER.EXE	2019/10/23 10:46	应用程序	277 KB
Readme.txt	2020/1/9 16:58	文本文档	1 KB

Figure 8 Double Click "CH341SER.EXE"

Step 2: If there is an indication that installation failed, please first uninstall the installation, then install again.

뤍 DriverSetup(X64)	– 🗆 ×				
Device Driver Install / UnInstall					
Select INF	CH341SER.INF ~				
INSTALL	WCH.CN  USB-SERIAL_CH340  01/30/2019, 3.5.2019				
UNINSTALL	1_ 01/00/2017, 0.5.2017				
HELP					

Figure 9 Driver Installation

#### **Download DALI Master PC Software**

DALI Master PC software can be downloaded from the following links, just copy and paste the link to the web browser on your PC.

If your Windows operating system is 64 bit, use the link below:

https://www.sunricher.com/media/resources/manual/V1.74-X64.zip

If your Windows operating system is 32 bit, use the link below:

https://www.sunricher.com/media/resources/manual/V1.74-X86.zip

### **Product Dimension**

